

**Little Sound Dj v4.9.3**

**Operating Manual**



# Little Sound Dj v4.9.3

Copyright © Johan Kotlinski <sup>1</sup>

January 9, 2017

<sup>1</sup>Aaron U made minor contributions. Thanks!



# Contents

<b>1</b>	<b>Introduction</b>	<b>7</b>
1.1	Hi!	7
1.2	Important Notice	7
1.3	Game Boy Sound	8
1.4	Key Presses	8
1.5	Navigating the Program	9
1.6	Making Your First Sounds	10
1.7	Initial Troubleshooting	11
1.8	Hexadecimal Number System	12
<b>2</b>	<b>The Screens</b>	<b>13</b>
2.1	Screen Map	13
2.2	Starting and Stopping	14
2.3	Song Screen	14
2.4	Chain Screen	15
2.5	Phrase Screen	16
2.6	Instrument Screen	17
2.6.1	General Instrument Parameters	18
2.6.2	Pulse Instrument Parameters	19
2.6.3	Wave Instrument Parameters	20
2.6.4	Kit Instrument Parameters	21
2.6.5	Noise Instrument Parameters	22
2.6.6	Speech Instrument Parameters	22
2.7	Table Screen	23
2.7.1	Custom Envelope Example	23
2.7.2	Arpeggio Example	23
2.8	Groove Screen	25
2.9	Synth Screen	26
2.9.1	General Parameters	27
2.9.2	Start and End Parameters	27
2.10	Wave Screen	29

2.11	Project Screen . . . . .	29
2.11.1	Total Memory Reset . . . . .	32
2.12	File Screen . . . . .	32
2.12.1	Song List . . . . .	33
2.13	Border Information . . . . .	33
<b>3</b>	<b>Advanced Techniques</b>	<b>35</b>
3.1	Copy and Paste . . . . .	35
3.2	Cloning . . . . .	35
3.2.1	Deep vs. Slim-Cloning . . . . .	36
3.3	The Importance of Backups . . . . .	36
3.4	Muting, Soloing and Panning on the Fly . . . . .	36
3.5	Live Mode . . . . .	37
3.5.1	Chain Loops . . . . .	37
3.6	Creating Synthetic Drum Instruments . . . . .	38
3.6.1	Bass Drum . . . . .	38
3.6.2	Snare Drum . . . . .	38
3.6.3	Hi-Hats and Cymbals . . . . .	40
3.6.4	Taking Advantage of Tables . . . . .	40
<b>4</b>	<b>Overview of Key Presses</b>	<b>41</b>
<b>5</b>	<b>Commands</b>	<b>45</b>
5.1	A: Run tAble . . . . .	45
5.2	C: Chord . . . . .	45
5.3	D: Delay . . . . .	46
5.4	E: Amplitude Envelope . . . . .	46
5.4.1	For Pulse and Noise Instruments . . . . .	46
5.4.2	For Wave Instruments . . . . .	46
5.5	F: Wave Frame . . . . .	46
5.5.1	For Kit Instruments: . . . . .	46
5.5.2	For Wave Instruments: . . . . .	47
5.6	G: Groove Select . . . . .	47
5.7	H: Hop . . . . .	47
5.7.1	H in Phrases . . . . .	47
5.7.2	H in Tables . . . . .	48
5.8	K: Kill Note . . . . .	48
5.9	L: Slide . . . . .	48
5.10	M: Master Volume . . . . .	49
5.11	O: Set Output . . . . .	49
5.12	P: Pitch Bend/Pitch Shift . . . . .	49

5.13	R: Retrig the Latest Played Note . . . . .	49
5.14	S: Sweep/Shape . . . . .	50
5.14.1	Pulse Instruments . . . . .	50
5.14.2	Kit Instruments . . . . .	50
5.14.3	Noise Instruments . . . . .	50
5.15	T: Tempo . . . . .	50
5.16	V: Vibrato . . . . .	51
5.17	W: Wave . . . . .	51
5.18	Z: RandomiZe . . . . .	51
<b>6</b>	<b>Synchronization</b> . . . . .	<b>53</b>
6.1	Game Boy to Game Boy Sync . . . . .	53
6.1.1	Activating Sync . . . . .	53
6.1.2	Using Sync with Both Carts in Song Play Mode . . . . .	54
6.1.3	Using Sync with Both Carts in Live Play Mode . . . . .	54
6.2	MIDI Sync . . . . .	54
6.3	Nanoloop Sync . . . . .	55
6.4	Analog In . . . . .	55
6.5	Analog Out . . . . .	55
6.6	Keyboard Control . . . . .	56
6.6.1	Keyboard Note Layout . . . . .	56
<b>7</b>	<b>Speech Programming</b> . . . . .	<b>59</b>
7.1	Introduction . . . . .	59
7.2	Linguistics . . . . .	59
7.3	Programming Words . . . . .	59
7.4	Guidelines for Using the Allophones . . . . .	61
7.4.1	Short vowels . . . . .	61
7.4.2	Long vowels . . . . .	61
7.4.3	R-colored vowels . . . . .	61
7.4.4	Resonants . . . . .	62
7.4.5	Voiced fricatives . . . . .	62
7.4.6	Voiceless fricatives . . . . .	62
7.4.7	Voiced stops . . . . .	63
7.4.8	Voiceless stops . . . . .	63
7.4.9	Affricates . . . . .	63
7.4.10	Nasal . . . . .	64
<b>8</b>	<b>The Sample Kits</b> . . . . .	<b>65</b>





# Chapter 1

## Introduction

### 1.1 Hi!

First of all, thanks for trying out Little Sound Dj!

A lot of effort has been put into making this program as powerful and fast-worked as possible. If you don't have previous experience from similar "tracker"-like music editors, the amount of new concepts may seem a bit overwhelming at first. Please, try not to stress about it. Learn step by step, keep it fun and progress at your own pace. Within days, you should know enough about the program to make your own first songs.

This manual is mostly written as an absolute beginners guide, but also as a reference that covers everything in the program. However, there still is a lot of information that would not fit into a manual like this. I highly recommend checking out the user-maintained Wiki site at <http://wiki.littlesounddj.com> - it contains material like tutorials, tips and tricks, and hardware related DIY projects. Also, the LSDj mailing list at <http://launch.groups.yahoo.com/groups/lsdj> is useful for getting in touch with other users. If you have questions or bug reports, please e-mail [info@littlesounddj.com](mailto:info@littlesounddj.com).

Happy tracking!

*/Johan*

### 1.2 Important Notice

Turning off the Game Boy while playing may cause your songs to be lost, so please avoid that. Also, it is best to avoid using the program when batteries are low enough to risk that the Game Boy shuts down itself. Low battery

level is indicated by the red light on your Game Boy becoming faint, or the screen becoming dim.

### 1.3 Game Boy Sound

The Game Boy sound chip has four channels, each with 4-bit resolution.

**Pulse Channel 1** Square wave with envelope and sweep functions.

**Pulse Channel 2** Square wave with envelope function.

**Wave Channel** Soft synthesizer, sample playback and speech synthesis.

**Noise Channel** Noise with envelope and shape functions.

### 1.4 Key Presses

In this documentation, key presses are marked up in this fashion:

**A** A button

**B** B button

**START** start button

**SELECT** select button

**LEFT** left arrow

**RIGHT** right arrow

**UP** up arrow

**DOWN** down arrow

**CURSOR** pressing any arrow key

**LEFT/RIGHT** pressing left or right arrow

**UP/DOWN** pressing up or down arrow

**SELECT+A** pressing A while holding SELECT

**SELECT+(B,B)** pressing B twice, while holding SELECT

## 1.5 Navigating the Program

After starting up LSDj, you should be facing a screen like the one in figure 1.1.




Figure 1.1: Song Screen

The SONG title at the top left of the window indicates that this is the song screen, the window where you arrange your songs. The four columns with dashes each represent a Game Boy sound channel. There are two pulse wave channels, one custom wave channel (which uses sampled drum kits or soft-synthesized wave forms), and one noise channel. You can move around between the different channels using the cursor key.



Figure 1.2: Screen Map

Little Sound Dj uses several screens, which are laid out on a  $5 \times 3$  map, displayed in the bottom right of the screen (figure 1.2). The most useful screens are laid out in the middle row, also called the main row. It contains the song, chain, phrase, instrument and table screens. These screens are ordered after level detail. The leftmost song screen presents an overview over the entire song, whereas the rightmost table screen is for detailed instrument programming. You can navigate between the different screens by holding SELECT and pressing the cursor key.

The song, chain and phrase screens are used for sequencing, and work together in a tree-structure fashion. The phrase screen is a 16-step sequencer where the actual note data is entered. The chain screen is a 16-step sequencer where you can enter sequences of phrases to be played back. The song screen is a 256 step long sequencer, where you enter sequences of chains to be played back.

## 1.6 Making Your First Sounds

Navigate to the song screen, and put the cursor on the PU1 column. Now tap the A button twice to insert a new chain. The digit 00 should appear at the cursor. You can now edit chain 0 by pressing SELECT+RIGHT and entering the chain screen. There, go through the same procedure: tap A twice to insert a new phrase, and press SELECT+RIGHT to go to the phrase screen.

PHRASE	NOTE	INSTR	CMD	PU1
0	---	I---	-00	CP0
1	---	I---	-00	J128
2	---	I---	-00	1
3	---	I---	-00	2
4	---	I---	-00	W
5	---	I---	-00	N
6	---	I---	-00	
7	---	I---	-00	
8	---	I---	-00	
9	---	I---	-00	
A	---	I---	-00	
B	---	I---	-00	
C	---	I---	-00	
D	---	I---	-00	
E	---	I---	-00	
F	---	I---	-00	

Figure 1.3: Phrase Screen

In the phrase screen, you can enter notes to be played back. Move the cursor to the note column and press A to enter a note. The text C-3 will appear: C being the note, and 3 the octave. Press START to play back the phrase. Note how the phrase is played back from the top of the screen to the bottom. You can change the note value by holding A and pressing the cursor button. A+LEFT/RIGHT changes the note, and A+UP/DOWN changes octave.

You can now try to move the cursor up and down and insert more notes in other positions. If you want to delete a note, press A while holding B. When you have finished listening, press START again to stop the phrase.

The clean pulse sound might get a bit dull after while. Let's move on to the instrument screen by pressing SELECT+RIGHT.




Figure 1.4: Instrument Screen

In the instrument screen, we can make the sound a little bit more interesting. Try to change the envelope and wave fields by moving the cursor there and pressing A+LEFT/RIGHT. Try to modify the envelope setting from A8 to A3. Now, press START again to hear any change in sound. The sound should now be more bouncy.

The type field sets the instrument type. The instrument types are specific for different channels – pulse instruments should only be played back in the pulse channels, wave and kit instruments in the wave channel, and noise instruments in the noise channel.

Let's try out the sampled drum kits. Now, we have to change channel to the wave channel. Go back to the song screen, move the cursor over to the wave channel, and create a new chain and a new phrase the way you did before (tapping A twice on empty steps). Then, move over to the INSTR column in the phrase screen, and tap A twice to create a new instrument. Press SELECT+RIGHT to edit that instrument, change the instrument type to KIT by pressing A+RIGHT once on the type field, then go back to the phrase screen. Now, you should be able to enter drum sounds the same way you entered notes before.

## 1.7 Initial Troubleshooting

Does Little Sound Dj behave strangely? Here are some things to try.

- If your cartridge doesn't start up at all, and only shows a garbled Nintendo logo at startup, the problem might be oxide on the cartridge

pins. Try removing and re-inserting your cartridge about thirty, forty times.

- If the software behaves a little oddly, instruments don't seem to work as supposed or similar, do a full reset of the internal memory. This is done by navigating to the project screen and pressing SELECT+A on the LOAD/SAVE FILE button.
- Search for more help on the Little Sound Dj Wiki (<http://wiki.littlesounddj.com>) or in the lsdj-backup Yahoo! Group (<http://groups.yahoo.com/>).

## 1.8 Hexadecimal Number System

Before moving on to the next chapter, now is a good time to get introduced with the hexadecimal number system that Little Sound Dj uses for representing values.

The hexadecimal number system works just the same way as the traditional decimal number system. The only difference is that it's base is 16 instead of 10. This means it consists of 16 unique symbols: the digits 0 to 9, followed by the letters A to F. For clarity, this manual will mark hexadecimal values with a dollar sign. As an example, let's print a table of numbers – first with decimal digits, then with hexadecimal digits...

Decimal	1	2	3	4	5	6	7	8	9	10
Hexadecimal	\$1	\$2	\$3	\$4	\$5	\$6	\$7	\$8	\$9	\$A
Decimal	11	12	13	14	15	16	17	18	19	20
Hexadecimal	\$B	\$C	\$D	\$E	\$F	\$10	\$11	\$12	\$13	\$14

Note that the hexadecimal and decimal values are really equal; just the representations differ. The reason to use the hexadecimal system here is to save screen space; with hexadecimal numbers, it is possible to represent every byte value using no more than two digits. (The value range is 0 to 255 – that is, \$0 to \$FF.)

Representing negative numbers with two digits only can be a problem. In Little Sound Dj, the numbers are wrapping. That means, when subtracting one from the smallest possible number (\$0), it will jump to the highest possible value (\$FF). So \$FF can represent -1 as well as 255, depending on the situation.

If you don't get all this immediately – please don't worry too much – it will become clear to you as you spend time with the program.

# Chapter 2

## The Screens

As stated before, Little Sound Dj has several screens, laid out in a screen map of size  $5 \times 3$ . You can navigate between the screens by pressing SELECT+CURSOR.

### 2.1 Screen Map

Project		Wave	Synth		
Song	Chain	Phrase	Instr.	Table	← Main Row
Groove					

The song, chain and phrase screens are used for sequencing and arranging. The wave, synth, instrument and table screens are used for sound programming.<sup>1</sup>

The remaining screens, project and groove, have more general purposes. The bulk of your activities will however probably be in the so-called "main row," in the middle of the map, as that's where the composing is done.

---

<sup>1</sup>There are also three hidden screens, not shown on the map: The file, word and help screens. We will get back to these later.

## 2.2 Starting and Stopping

When pressing **START** in the song screen, Little Sound Dj will always try to play all four channels. When pressing **START** in the other screens, Little Sound Dj will only try to play the channel that's indicated in the three-letter field at the right edge of the screen (**PU1**, **PU2**, **WAV** or **NOI**).

If you want to start playing all four channels from some other screen than the song screen, you can do that by pressing **SELECT+START**.

## 2.3 Song Screen




Figure 2.1: Song Screen

The song screen is the highest level of the sequencer. This is where you arrange your songs.

The screen contains four columns, one for each channel. The columns contain lists of chains, which will be played from top to down. Different chains are used for different channels.

To insert a chain, move the cursor to an empty step and press **A**. If you want to add a new chain, press **A** twice. To edit a chain, move the cursor to the chain number and press **SELECT+RIGHT**. To remove a chain, you can either press **A** twice or press **B+A**.

To start or stop playing all channels in the song screen, press **START**. To instantly re-start all channels in the song screen, press **SELECT+START** (this has the same effect as pressing **START**, **START** quickly).



TIP!



- You can pull up down-below chains by pressing B+A on an empty step.
- You can add or remove song screen bookmarks by tapping B three times (B, B, B). This will shade the area under the cursor.

The number of rows in the song screen is limited to 255 (\$00-\$FE).

## 2.4 Chain Screen

Chains are used for stringing phrases together, thus creating a unit built out of many phrases. A chain can represent a longer rhythm block, a melody or a bass line.

The chain screen contains two columns. The first column contains the list of phrases that are to be stringed together, while the second column transposes the phrase on the same row.

CHAIN	PAT	TSP
0	03	05
1	04	00
2	05	00
3	06	00
4	--	00
5	--	00
6	--	00
7	--	00
8	--	00
9	--	00
A	--	00
B	--	00
C	--	00
D	--	00
E	--	00
F	--	00

PU1  
CP0  
J128  
1  
2  
N

P  
SC  
G

Figure 2.2: Chain Screen

Example: The chain in figure 2.2 would play phrase 3, adding 5 semitones to each note, and then play each of the phrases 4, 5, 6, without transposing.

To add a phrase to the chain, move the cursor to an empty step and press A. If you want to insert a new phrase, press A twice. To edit a phrase, move the cursor to the phrase number and press SELECT+RIGHT.

When editing a chain, you can go to the chain in a neighboring channel by pressing B+LEFT/RIGHT. It is also possible to go to the next or previous chain in the song screen by pressing B+UP/DOWN.

The different channels all share the same set of chains; that is, no chain is ever assigned to a specific channel. The number of chains is limited to 128 (\$00-\$7F).

## 2.5 Phrase Screen

PHRASE 00			PU1
NOTE	INSTR	CMD	
0	---	-00	CP0
1	---	-00	J128
2	---	-00	1
3	---	-00	2
4	---	-00	W
5	---	-00	N
6	---	-00	
7	---	-00	
8	---	-00	
9	---	-00	
A	---	-00	
B	---	-00	
C	---	-00	
D	---	-00	
E	---	-00	
F	---	-00	

The phrase screen is the most fundamental part of the sequencer; this is where you enter the actual note data. The phrase screen has four columns: the note column, the instrument column, and the command and command value columns.

The different channels all share the same set of phrases; that is, any phrase may be played back on any channel. A phrase might however sound very different, depending on the channel it is played back on. Example: If you have programmed a phrase to play a melody using a pulse instrument, that phrase can be played back in either of the pulse channels with good results, but it usually doesn't make sense to play back the phrase in the wave or noise channels.

The note column may look different depending on which instrument type is used. Most instruments present the note followed by octave. Instruments that play back samples (KIT, SPEECH) do however present the sample names instead.

The instrument column is used for selecting instruments. In total, you can use 64 different instruments, editable in the instrument screen.



TIP!

- It is possible to change the pitch without retriggering the instrument by leaving the instrument column empty.

The command columns can be used to add effects to your phrase. For example, the K command kills the sound on the channel.

The number of phrases is limited to 255 (\$00-\$FE). The number of the phrase that is being edited is displayed in the top left corner of the screen.



TIP!

- All phrases are 16 steps long by default, but it is also possible to set a shorter length by using the H (hop) command.

## 2.6 Instrument Screen




Figure 2.3: Instrument Screen

There are five types of instruments available:

**PULSE** This instrument type produces pulse waves, and is used in pulse channels 1 and 2.

**WAVE** This instrument type can play back waves synthesized using the synth screen. It is used in the wave channel.

**KIT** This instrument type plays sampled kits, stored in ROM. (The samples are stored in 4 bits, 11,468 kHz.) It is used in the wave channel.

**NOISE** This instrument type produces filtered noise, and is used in the noise channel.

**SPEECH** This instrument is locked to instrument number \$40, and is used for programming speech. For learning how to generate speech, please read [chapter 7](#).

You can change the instrument type by going to the type row and pressing A+CURSOR.

Remember that instruments don't automatically play in the right channel. For example, if you want to use a kit instrument to play drum samples, you have to do the following:

1. Go to the song screen, move cursor to the wave column, and insert a new chain by tapping A twice.
2. Edit the chain by pressing SELECT+RIGHT.
3. Insert a new phrase by tapping A twice.
4. Edit the phrase by pressing SELECT+RIGHT. Now, you have a new phrase that is mapped to the wave channel.
5. Create a new instrument by moving the cursor to the instrument column and tapping A twice.
6. Press SELECT+RIGHT to edit the instrument.
7. Change the instrument type to KIT.
8. Go back to the phrase screen to start using your new instrument.



TIP!

- *In the instrument screen, press SELECT+B to copy instruments and SELECT+A to paste.*

### 2.6.1 General Instrument Parameters

These parameters are used in most instrument types.

**NAME** Name the instrument by pressing A. This is useful for keeping track of your instruments. The instrument name will also be shown in the border when selecting instruments in the phrase screen.

**TYPE** Use this to specify the instrument type.

**LENGTH** Change the sound length.

**PAN** Pan the sound to left/right/both/none speakers. (Use the headphone output to hear the difference!)

**VIB. TYPE** Change the effect and speed of the vibrato (V), pitch bend (P) and slide (L) commands. The high frequency (HF) setting can create very interesting timbres. The other settings are more conventional, but just as useful. Pressing A+UP/DOWN changes the direction of the vibrato.

**TABLE** If set to values other than OFF, Little Sound Dj will start running the specified table when a note is played. If you want to edit the table, press SELECT+RIGHT to get to the table screen. If you want to use a new table, tap A twice.

**AUTOMATE** This option extends the table functionality. When automation is activated, Little Sound Dj advances through the tables by one step for each time the instrument is triggered.

## 2.6.2 Pulse Instrument Parameters




Figure 2.4: Pulse Instrument Screen

**ENVELOPE** The first digit sets initial amplitude (0-\$F); the second digit sets release (0, 8: none, 1-7: decrease amplitude, 9-\$F: increase amplitude).

**WAVE** Choose the wave type to be used.

**SWEEP** Modulate the frequency. This only works on pulse channel 1. See Sweep/Shape (S) command documentation for further information.


The detune settings can be used to create interesting phase effects, when the same phrase is played on both pulse channels:

**PU2 TUNE** Detune pulse channel 2 in semitones.

**PU FINE** Detune pulse channel 1 downwards, channel 2 upwards.

### 2.6.3 Wave Instrument Parameters

The wave instrument can play back synth sounds generated by the soft synthesizer found in the SYNTH screen.



**VOLUME** Set amplitude (0=0%, 1=25%, 2=50%, 3=100%)


**SYNTH** Select the synth sound to play back. To edit the synth sound being used, press SELECT+UP to go to the SYNTH screen. If you want to use a new synth, tap A twice.

**PLAY** How to play back the synth sound: Once, loop, pingpong loop or manual. By selecting manual, only the first wave in the synth sound will be played, allowing you to step through the sound manually using the F command.

**LENGTH** Set the length of the synth sound.

**REPEAT** Set the loop point of the synth sound.

**SPEED** Set how fast the synth sound should be played back.



### 2.6.4 Kit Instrument Parameters

**KIT** Choose the kits to use. The first kit will be used in the left note column in the phrase screen; the second kit will be used in the right note column in the phrase screen.

**PITCH** Pitch shift.

**OFFSET** Set the start loop point. If LOOP is set to OFF, this value can be used for skipping the initial part of a sound.

**LEN** Set the sound length. (AUT=always play the sample to its end.)

**LOOP** Loop the sample. (OFF=don't loop, ON=loop sound and start playing from custom offset, ATK=loop sample and start playing from the beginning.)

**SPEED** Select full speed or half speed.

**DIST** Select the algorithm that should be used when two kits are mixed together. CLIP is the default type. SHAPE and SHAPE2 sound similar to CLIP, but with more high frequencies and less bass. WRAP can be used to add some interesting digital distortion. When pressing A+(LEFT, LEFT) while CLIP value is selected, the program will jump out of range and play back sound from raw memory when clipping.



TIP!

- For those running LSDj on emulator or with backup gear, there is a Java application for replacing the original sample kits available at <http://littlesounddj.com/lsd/latest/lsd-patcher/>.

## 2.6.5 Noise Instrument Parameters




Figure 2.5: Noise Instrument Screen

**ENVELOPE** First digit is initial amplitude (0-\$F); second digit is release (0, 8: none, 1-7: decrease amplitude, 9-\$F: increase amplitude).

**SHAPE** Alter the noise shape. The first digit alters the pitch, the second period alters the randomness.

**S CMD** When set to **FREE**, altering noise shape by the **S** command (5.14.3) can in some circumstances<sup>2</sup> mute the sound. When set to **STABLE**, the **S** command is limited so that the sound will never be muted by accident.

## 2.6.6 Speech Instrument Parameters

For information about how to generate speech, please read chapter 7.

The number of instruments is limited to 64 (hexadecimal: \$00-\$39).

<sup>2</sup>The exact circumstances for when sound can get muted is when a shape that ends with digit 8-F is changed so that it ends with digit 0-7. In that case, the odds that the sound will get muted is 1 out of 256.



## 2.7 Table Screen

Tables are essentially sequences of transposes, commands and amplitude changes, which can be executed at any speed (by default, one tick per step) and applied to any channel. If you want to, you can assign tables to instruments (by changing the TABLE setting in the instrument screen), so that a table will be started every time you play the instrument. It is the key to creating truly complex instruments in Little Sound Dj.

Tables contain six columns, which are executed from top to bottom. The first column is the envelope column, by which it is possible to create custom amplitude envelopes. Next is the transpose column, that can be used to transpose the note being played by a given number of semitones. The other columns are command columns, just like the one in the phrase screen.

By default, each step will be executed in one tick, but it is also possible to select a different groove using the G (groove) command.



TIP!

- *The transpose column has special functionality when using KIT or NOISE type instruments. For KIT, the transpose column works as a pitch shifter. For NOISE, the transpose column has the same effect as issuing the S (shape) command.*

### 2.7.1 Custom Envelope Example

The first digit in the envelope column sets the amplitude; the second digit sets for how many ticks that amplitude should remain.

The table in figure 2.6 creates an amplitude envelope with short attack and medium sustain. It could be used for a bass instrument.

### 2.7.2 Arpeggio Example

A typical use for tables is to create arpeggios. This is a musical term for playing notes very fast, so that the listener will get the impression that a chord is played. The table in figure 2.7 would emulate striking a major chord.

Shorter arpeggios can just as well be created using the C (chord) command in phrases (see 5.2 for example). Tables however still have to be used for creating longer arpeggios.

To view different tables, press B+CURSOR.

TABLE 00				PU1
	VOL	TSP	CMD	
0	51	00	-00	-00
1	01	00	-00	-00
2	71	00	-00	-00
3	64	00	-00	-00
4	46	00	-00	-00
5	33	00	-00	-00
6	22	00	-00	-00
7	15	00	-00	-00
8	05	00	-00	-00
9	00	00	-00	-00
A	00	00	-00	-00
B	00	00	-00	-00
C	00	00	-00	-00
D	00	00	-00	-00
E	00	00	-00	-00
F	00	00	-00	-00

J 128  
1  
2  
W  
N

P  
SCPT  
G

Figure 2.6: Table Envelope Example

TABLE 00				PU1
	VOL	TSP	CMD	
0	00	00	-00	-00
1	00	04	-00	-00
2	00	07	-00	-00
3	00	09H	00	-00
4	00	00	-00	-00
5	00	00	-00	-00
6	00	00	-00	-00
7	00	00	-00	-00
8	00	00	-00	-00
9	00	00	-00	-00
A	00	00	-00	-00
B	00	00	-00	-00
C	00	00	-00	-00
D	00	00	-00	-00
E	00	00	-00	-00
F	00	00	-00	-00

J 128  
1  
2  
W  
N

P  
SCPT  
G

Figure 2.7: Arpeggio Example



TIP!

- To make an instrument attack sound more interesting, it can be useful to let the first row in a table be transposed a few steps up or down.
- There is a shortcut between the phrase and table screens. Press SELECT+RIGHT on an A command in the phrase screen to edit the table selected with the A command. To jump back, press SELECT+LEFT.

The number of tables is limited to 32 (\$00-\$1F).

## 2.8 Groove Screen

Grooves define the speed with which your phrases and tables are played back. They can be used for giving your songs some extra swing. The different sound channels do not need to be synchronized to each other; this means that you can use a separate groove for each phrase and table.




Figure 2.8: Groove Screen

For understanding the groove concept, you need to know that the sequencer's time handling is based on an abstract time period called *tick*. The length of a tick varies with the song tempo, but is typically around 1/60th of a second. In the groove screen, you can specify for how many ticks each note step should be played. The groove in figure 2.8 would make the sequencer spend approximately 6/60th of a second on every note step.

You can also use the groove screen to create custom rhythms. The groove in figure 2.9 would make the sequencer spend 8/60th of a second




Figure 2.9: Swing Example

on even note steps, and 5/60th of a second on odd note steps. This would create a swing feeling. With thoughtful programming, grooves can also be used to create triplets and other complex rhythm structures.

Groove 0 is the default groove for all phrases. If you want to, you can easily switch to another groove by using the groove (G) command in the phrase screen.

You can select the groove you wish to edit by pressing B+CURSOR.



TIP!

- Pressing A+UP/DOWN will change the swing percentage, while keeping the total number of ticks – and thus, the resulting song speed – constant. (Example: Original value is 6/6 = 50%. Press A+UP. Now the value changes to 7/5 = 58%!)
- If you switch to the groove screen when the cursor is on a G command in the phrase or table screens, Little Sound Dj will display the groove that is selected with the groove command.

## 2.9 Synth Screen

The synth screen features a soft synthesizer that generates sounds to be played back by the wave instruments. In total, there are 16 synth programs. You can choose the program to edit by pressing B+CURSOR.



TIP!

- Each synth program uses \$10 waves. Synth program 0 uses waves \$00-\$0F, synth program 1 uses waves \$10-\$1F, and so on. It is possible to look at the resulting synth sounds in the wave screen (Section 2.10).



Figure 2.10: Synth Screen

### 2.9.1 General Parameters

**WAVE** Square, saw tooth or triangle.

**FILTER** Low-pass, high-pass, band-pass or all-pass.

**Q** Resonance control. Boost the signal around the cutoff frequency, to change how bright or dull the wave sounds.


**DIST** Use clip or wrap distortion.

**PHASE** Compress the waveform horizontally. It is applied after filtering with Q and cutoff. See figure 2.11 for examples.


### 2.9.2 Start and End Parameters

Use these settings to specify values for the start and end of the sound. The program will then create a smooth fade between the start and end values.


**VOLUME** Wave volume.




(a) Phase example. Original wave.



(b) NORMAL phasing. Compress horizontally, generate once.



(c) RESYNC phasing. Compress horizontally, loop.



(d) RESYN2 phasing. Loop, but don't compress.

Figure 2.11: Phase Examples

**CUTOFF** Filter cutoff frequency.

**PHASE** 0 = no phase, \$1F = maximum phase. See figure 2.11 for examples.

**VSHIFT** Shift the waveform vertically. See figure 2.12 for examples.

## 2.10 Wave Screen

In the wave screen, you can view and edit the individual waveforms of the synth programs. There are 16 (\$10) synth programs, and each program has \$10 waves. This means that synth sound 0 uses waves \$0-\$F, synth sound 1 uses waves \$10-\$1F, and so on.

To change a value, press UP/DOWN. To flip a value vertically, press A+UP/DOWN. B+CURSOR navigates between different waves.

It is possible to modify multiple values at once, using the regular key presses:

**SELECT+B** Start selection.

**SELECT+B,B** Select the entire wave.

**B** Copy selection to clipboard.

**UP/DOWN** Move selection up/down.

**A+UP/DOWN** Flip selection vertically.

**SELECT+A** Paste from clipboard.

## 2.11 Project Screen


The project screen (figure 2.13) contains settings that affect the entire program.

**TEMPO** Change the tempo. It is possible to set a new tempo either by pressing A+CURSOR, or by tapping the A button in pace with the desired tempo. When being slave in sync mode, it is possible to temporarily play a little faster or slower by pressing A+LEFT/RIGHT.


**TRANSPOSE** Adjust the pitch of the pulse and wave instruments, by a given number of semitones.



(a) Vshift example. Original wave.



(b) Vshifted wave. Vshift set to 40.



(c) Vshifted wave. Vshift set to 80.

Figure 2.12: Vshift Examples






Figure 2.13: Project Screen

**SYNC** Activate link-up over the serial port. (Read more about this in chapter 6!)

**CLONE** Select deep or slim chain cloning. Deep chain cloning will also clone the phrases of a chain when cloning, whereas slim cloning will re-use the old phrases. Read chapter 3 for a full explanation of cloning.

**LOOK** Change the font and color set.

**KEY DELAY** Set the delay time before key repeat is activated for the Game Boy buttons.

**KEY REPEAT** Set the key repeat speed for the Game Boy buttons.

**PRELISTEN** Play notes and instruments while entering them.

**HELP** Enter help screen. The help screen contains a quick reference for button presses and a command list.

**CLEAN SONG DATA** Clear all phrases and chains that are not used in the song. Also, if there are several phrases with the same content, they will be reduced to one.

**CLEAN INSTR DATA** Clear all instruments, tables, synths and waves that are not used in the song.

**LOAD/SAVE SONG** Enter file manager.<sup>3</sup>

This screen also contains two clocks. The **WORK TIME** clock displays the time Little Sound Dj has been used since the last memory reset, in hours and minutes. When playing, the clock is replaced by a **PLAY TIME** clock, which shows for how long the song has been playing. The **TOTAL** clock displays the time Little Sound Dj has been used in total, in days, hours and minutes.

### 2.11.1 Total Memory Reset

By pressing **SELECT+A** on the **LOAD/SAVE FILE** button, you can choose to reset all memory. This can be useful if your memory somehow gets scrambled, or your cartridge starts to behave strangely in other ways.

## 2.12 File Screen




Figure 2.14: File Screen

The file screen (figure 2.14) is entered by pressing the **LOAD/SAVE FILE** button in the project screen. The file screen is used for saving the song you are working on to the storage memory. It can also be used to load songs from the storage memory to the work memory. The file screen allows you to keep up to 32 songs on one cartridge.

<sup>3</sup>The file manager is only available for cartridges that have 1 Mbit SRAM or more. In case your cartridge doesn't have 1 Mbit SRAM, this button will be replaced with a **RESET MEMORY** button.

NOTE: The file screen is only available for cartridges that have 1 Mbit SRAM or more.

**FILE** Shows the file name of the song you are working on. The exclamation mark (!) indicates when changes have been made to a song.

**LOAD** Load a song. Press A, select the file to load and press A again.

**SAVE** Save song. Press A, select the slot to save to and enter the file name.

**DEL** Delete a song. Press A, select the file to delete and press A again.

**BLOCKS USED** Shows how much of the storage memory that is used. One block equals 512 bytes. The digits on the bottom are hexadecimal, meaning there is a total of  $\$BF * 512 = 97,792$  available bytes.

If you want to cancel an operation in this screen, simply press B.



TIP!

- There is a useful file manager application available at <http://littlesounddj.com/lzd/latest/lzd-manager/>.

### 2.12.1 Song List

The song list presents song name, version number and file size. When saving, the song is compressed, so the resulting file size will vary with different songs. If you want to start a new project, load from the (EMPTY) slot.

## 2.13 Border Information

A lot of useful data is displayed in the screen border (figure 2.15).

1. Screen name.
2. Phrase/chain/instrument/table/frame/groove number.
3. Active channel.



# Chapter 3

## Advanced Techniques

### 3.1 Copy and Paste

Little Sound Dj has a clipboard for temporary data storage. Pressing B+A will cut the value under the cursor and store it on the clipboard. The value can then be pasted by pressing SELECT+A.

In most screens, it is possible to mark up blocks by pressing SELECT+B and moving around the cursor. When having marked up a block, it can be copied to the clipboard by pressing B, or cut to the clipboard by pressing SELECT+A. The clipboard contents can then be pasted by pressing SELECT+A.

Some quick-mark button presses are implemented:

- SELECT+(B, B) = quick-mark a column or row.
- SELECT+(B, B, B) = quick-mark an entire screen.

When having marked a block, you can change all data inside that block by pressing A+CORSOR. This can be used, for example, to transpose several notes quickly.

### 3.2 Cloning

Cloning is a shortcut that can save you much unnecessary copy and paste action. It allows you to create copies of chains, phrases, instruments and tables directly from the song, chain, phrase and instrument screens.

Let's say you have a melody in chain 00, and you want to continue the song with the same melody, but a little changed. Then you copy 00 (SELECT+B, B) and paste one row down (SELECT+A), so you get:

00  
00

Now, place the cursor on the second 00, and press `SELECT+(B, A)`. You will now get a new chain (probably called 01) which is a copy of 00. Since it's a copy, you can play around with it as much as you want without touching 00.

### 3.2.1 Deep vs. Slim-Cloning

There are two different modes for cloning: slim-cloning and deep-cloning. You can select the mode in the project screen.

If you slim-clone 00, Little Sound Dj makes a new chain 01 that contains the same phrases as 00.

If you deep-clone 00, Little Sound Dj makes a new chain 00, and also clones the phrases within 00 into 01. That way, you can change 01's phrases without affecting 00.

The advantage of deep-cloning is that you have no risk of modifying old phrases by accident. The drawback is that it uses more phrases, so that you may run out of phrases faster. Also, your songs may take up more blocks when being saved using the file screen.

If you find yourself running out of phrases, try using `CLEAN SONG DATA` in project screen. (Section 2.11.)

## 3.3 The Importance of Backups

Some wise words from many peoples hard-earned experience: If you use Little Sound Dj on a Game Boy cartridge, it might be a good idea to examine backup options like the Transferer or the MegaMemory Card. Game Boy cartridges are often rather unstable, as they are depending on an internal battery that is likely to run out sooner or later. If you are serious about your music, you should do regular backups, or at least try to record your songs once in a while.

## 3.4 Muting, Soloing and Panning on the Fly

It is always possible to mute a channel temporarily by pressing `B+SELECT`. If the B button is released before `SELECT`, the channel will stay muted until B is pressed again.

Correspondingly, a channel can be played solo by pressing B+START. If the B button is released before START, the other channels will stay muted. If the START button is released first, all channels will be turned on again.

It is also possible to pan channels left or right, by pressing B+LEFT / RIGHT in the song screen.

## 3.5 Live Mode

The live mode is a special flavor of the song screen. It can be reached by pressing SELECT+LEFT while in the song screen. In the live mode, it is possible to start and stop playing chains one by one. In contrast to the usual song screen, the different channels can be started and stopped independently. It is also possible to jump between different song positions while playing, without causing audio glitches or lost synchronization.

To play a chain, move the cursor to the chain and press START. To stop playing a chain, go to that channel and press SELECT+START. If another chain is already playing, the starts and stops will be queued until that chain has been played through. If you want to queue until the next phrase end instead, tap START twice to speed up the switch.

To switch back to song mode from live mode, just press SELECT+LEFT while in the song screen.



TIP!

- To start or stop several chains at once, mark them before pressing START or SELECT+START. (Marking is described in section 3.1.)

### 3.5.1 Chain Loops

Using chain loops is a useful live mode technique. This technique is based on the fact that the song sequencer (when being in the live mode) won't rewind the song position all the way up to the first song sequencer step when encountering end of track; instead, it stops rewinding as soon as it encounters an empty step.

Example: We have a setup that looks like figure 3.1.

Assume that we start playing pulse channel 1 at song position 4. The player will now loop chains 2 and 3. Defining a number of such chain loops to alternate between would provide a good starting point for a live performance.

SONG	PU1	PU2	WAV	NOI	PU2
00	00	---	---	---	
01	01	---	---	---	
02	---	---	---	---	J 128
03	---	---	---	---	
04	02	---	---	---	1
05	03	---	---	---	2
06	---	---	---	---	W
07	---	---	---	---	H
08	---	---	---	---	
09	---	---	---	---	
0A	---	---	---	---	
0B	---	---	---	---	
0C	---	---	---	---	
0D	---	---	---	---	
0E	---	---	---	---	P
0F	---	---	---	---	S
					CPTT
					G

Figure 3.1: Chain Loop Example

## 3.6 Creating Synthetic Drum Instruments

Creating good-sounding drum instruments without using the sampled drum kits might be a bit tricky, if you've had no prior experience with drum synthesis. Nevertheless, it's a very useful technique once you know it. Here are some starting-out ideas.

### 3.6.1 Bass Drum

Use pulse channel 1 for creating bass drum sounds. The amplitude envelope should have a strong attack and fast decay - try setting it to \$C1. Wave should be 50-50 high/low, even though other waves can be used for making the instrument sound more distorted. The sweep value is maybe the most important part in creating a successful kick instrument. It should have a high initial frequency and decay. Try setting it to a value of \$E3, and playing the instrument at note C-6. For a more snappy sounding kick, try experimenting with the envelope and length parameters.

It is also possible to use the noise channel for creating bass drums. Feel free to experiment around.

### 3.6.2 Snare Drum

Use the noise channel for creating snare drum sounds. The amplitude envelope should have a strong attack and fast decay - try setting it to \$C1. Use the length parameter to create more snappy sounding snares. The



```

INSTRUMENT 00      PU1
NAME      [KICK]
TYPE      PULSE
ENVELOPE  C1
WAVE      [ ]
OUTPUT    LR
LENGTH   UNLIM
SWEEP     E3
VIB. TYPE HFA
PU2 TUNE   00
PU FINE   0
AUTOMATE  OFF
TABLE     OFF
    
```

(a) Bass Drum

```

INSTRUMENT 00      HOI
NAME      [SNARE]
TYPE      NOISE
ENVELOPE  D1
OUTPUT    LR
LENGTH   30
SHAPE    ED
S CMD    FREE
AUTOMATE  OFF
TABLE     OFF
    
```

(b) Snare Drum

```

INSTRUMENT 00      PU1
NAME      [HH]
TYPE      NOISE
ENVELOPE  91
OUTPUT    LR
LENGTH   16
SHAPE    FF
S CMD    FREE
AUTOMATE  OFF
TABLE     OFF
    
```

(c) Closed Hi-Hat

```

INSTRUMENT 00      HOI
NAME      [HH]
TYPE      NOISE
ENVELOPE  A3
OUTPUT    LR
LENGTH   UNLIM
SHAPE    FF
S CMD    FREE
AUTOMATE  OFF
TABLE     OFF
    
```

(d) Open Hi-Hat

```

INSTRUMENT 00      HOI
NAME      [CYM]
TYPE      NOISE
ENVELOPE  85
OUTPUT    LR
LENGTH   UNLIM
SHAPE    ED
S CMD    FREE
AUTOMATE  OFF
TABLE     OFF
    
```

(e) Cymbal

```

TABLE 00      HOI
VOL  TSP CMD  CMD
0  00  F0-00  -00
1  00  00H00  -00
2  00  00-00  -00
3  00  00-00  -00
4  00  00-00  -00
5  00  00-00  -00
6  00  00-00  -00
7  00  00-00  -00
8  00  00-00  -00
9  00  00-00  -00
A  00  00-00  -00
B  00  00-00  -00
C  00  00-00  -00
D  00  00-00  -00
E  00  00-00  -00
F  00  00-00  -00
    
```

(f) Snare Drum Table

Figure 3.2: Synthetic Drum Instruments

shape parameter can be used for adjusting the timbre - shape values close to \$EC might prove useful.

### 3.6.3 Hi-Hats and Cymbals

Hi-hats are created using the noise channel. Use a shape value of \$FF for selecting a timbre with high frequency content. Change the envelope and length parameters for creating the desired amplitude envelope. For emulating cymbals, use a shape value near \$EE to create a somewhat rougher timbre.

### 3.6.4 Taking Advantage of Tables

For adding that extra punch to snares, you can use a table that uses the transpose column to change the noise shape rapidly. (See figure 3.2f.)

# Chapter 4

## Overview of Key Presses

This is an overview of key presses valid in the phrase screen. The key pressing philosophy expressed here is used as consistently as possible throughout the entire program.

### Editing Notes

A insert note on empty step

A+RIGHT note up

A+LEFT note down

A+UP octave/+10 up

A+DOWN octave/-10 down

B+A cut note to clipboard

### Marking blocks

SELECT+B start marking

SELECT+(B, B) mark row

SELECT+(B, B, B) mark all

**When Having Marked a Block...**

**A+LEFT** all marked down

**A+RIGHT** all marked up

**A+UP** all marked octave/+10 up

**A+DOWN** all marked octave/-10 down

**Copy/Paste Action**

**B** copy marked block to the clipboard

**SELECT+A** cut the marked block to the clipboard

**SELECT+(B, B, B, B)** copy the entire screen to the clipboard

**SELECT+A** paste from the clipboard

**Switching Phrases**

**B+LEFT** view the phrase in the leftmost channel

**B+RIGHT** view the phrase in the rightmost channel

**B+UP** view previous phrase in chain

**B+DOWN** view next phrase in chain

**Start/Stop in Song Mode**

**START** start/stop playing this phrase

**SELECT+START** start/stop playing all channels

**Start/Stop in Live Mode**

**START** start playing selected chain after next chain end

**START, START** start playing selected chain after next phrase end

**SELECT+START** stop playing current chain when it ends

**SELECT+(START, START)** stop playing current chain after next phrase end

## Muting and Soloing

**B+SELECT** mute this channel

**B+START** solo this channel



# Chapter 5

## Commands

Commands can be used in phrases and tables for altering the sound. There is a lot of power hidden in the commands, so it is suggested that you skim through this chapter at least once to get an idea of what they can do for you.



TIP!

- *Tapping A on a command letter will display a scrolling help text in the top of the screen. A+CURSOR can then be used to browse through the existing commands. The text can be paused by holding SELECT.*

### 5.1 A: Run tAble

Run a table. This command can be used in phrases, or inside a table, for jumping to another table.

**A03** run table 3

### 5.2 C: Chord

Produce chords by doing a simple arpeggio that extends the base note with the given semitones.

**C37** plays a minor chord: 0, 3, 7, 0, 3, 7, 0, 3, 7, ...

**C47** plays a major chord: 0, 4, 7, 0, 4, 7, 0, 4, 7, ...

**C0C** plays 0, 0, C, 0, 0, C, 0, 0, C, ...

**CC0** plays 0, C, 0, C, 0, C, ...

**CCC** plays 0, C, C, 0, C, C, 0, C, C, ...

## 5.3 D: Delay

Delay the triggering of a note with the given number of ticks.

## 5.4 E: Amplitude Envelope

This command functions in two different ways, depending on which instrument type it is used on.

### 5.4.1 For Pulse and Noise Instruments

The first value digit sets the initial amplitude (0=min, \$F=max); the second digit sets the release (0,8: no change, 1-7: decrease, 9-\$F: increase).

### 5.4.2 For Wave Instruments

**E00** volume 0%

**E01** volume 25%

**E02** volume 50%

**E03** volume 100%

## 5.5 F: Wave Frame

This command can be used on wave and kit instruments only.

### 5.5.1 For Kit Instruments:

Modify the start offset of the sample.



### 5.5.2 For Wave Instruments:

Change the wave frame that's being played on the wave channel. This command is relative, meaning that the command value will be added to the current frame number. This can be used for playing through synth sounds manually.



TIP!

- *Since a synth sound contains 16 (\$10) waves, issuing the command F10 will in effect jump to the next synth sound.*

Example:

**F01** If wave frame 3 is being played, advance 1 frame and start playing frame number 4.

## 5.6 G: Groove Select

Select the groove to use when playing phrases or tables.

Example:

**G04** select groove 4

## 5.7 H: Hop

H hops to a new play position. It can also be used to stop playing.

### 5.7.1 H in Phrases

**H00-H0F** Hop to next phrase. The digit sets destination phrase step.

**H10-HFE** Hop back within the phrase. The first digit sets number of times to hop back, the second digit sets destination step.

**HFF** Stop playing song (or channel, if in live mode).



TIP!

- *If you want to compose in waltz time (3/4), put H00 commands on step C in every phrase.*

### 5.7.2 H in Tables

In the table screen, H is used for creating table loops. The first digit sets how many times the hop should be done before moving on; 0 means “forever.” The second digit sets the table step to jump to. Loops can be nested; that is, you can have smaller loops inside bigger ones.

Example:

**H21** hop twice to table position 1.

**H04** hop to table position 4 forever.

## 5.8 K: Kill Note

Example:

**K00** kill note instantly

**K03** kill note after 3 ticks

## 5.9 L: Slide

The L command works on pulse and wave instruments only. It performs a pitch bend that stops when it reaches a given note.

Example:

```
C-4 ---
F-4 L04
--- ---
C-4 L03
```

This will result in a pitch bend that starts with C-4, bends to F-4 with the speed 4, and then bends back to C-4 with speed 3.

Warning: If using the L command next to an empty note value (“—”), results will be undefined.

## 5.10 M: Master Volume

This command changes the master output volume. The first digit modifies the left output, the second digit the right. The volume can either be set with an absolute value, or changed by a relative value.

Values 0-7 are used to specify absolute volumes. Values 8-\$F give the volume a relative change; 8 is no change, 9-\$B increase, \$D-\$F decrease.

Examples:

**M77** maximize volume

**M08** minimize left volume, leave right volume unchanged

**M99** increase volume with 1 step

**MFE** decrease left volume with 1 step, right volume with 2 steps

## 5.11 O: Set Output

Pan channel to left, right, none or both outputs.

## 5.12 P: Pitch Bend/Pitch Shift

The Pitch Bend command works on pulse and wave channels only. When it is used on *KIT* instruments, it sounds more like a pitch shifter.

Example:

**P02** bend up pitch with speed 2

**PFE** bend down pitch with speed 2 (\$FE=-2)

## 5.13 R: Retrigger the Latest Played Note

Play the latest played note again. The first digit modulates the volume (0=no change, 1-7=increase, 8-\$F=decrease). The second digit sets a period for the retriggering, zero being the fastest.

Example:

**R00** very fast retriggering

**RF3** medium speed retriggering, decreasing amplitude (echo effect)

## 5.14 S: Sweep/Shape

This command has different effects for different instrument types.

### 5.14.1 Pulse Instruments

S modulates pitch, using the Game Boy hardware. It is useful for creating bass drums and percussion. The first digit affects pitch, the second changes pitch bend velocity.

Note: S has no effect when being used in pulse channel 2!

### 5.14.2 Kit Instruments

S changes the loop points. The first digit modulates the offset value; the second digit modulates the loop length. (1-7=increase, 9-\$F=decrease.) Used creatively, this command can be very useful for creating a wide range of percussive and timbral effects.

### 5.14.3 Noise Instruments

On the noise channel, S works like a noise shape filter. The first digit alters pitch, the second digit alters the randomness. The command is relative, meaning that the pitch/randomness values will be added to the currently used values.

In some cases, this command can randomly mute the sound. If that becomes a problem, set S CMD to STABLE in instrument screen.

## 5.15 T: Tempo

Change the tick frequency so that the given BPM will be produced. The BPM setting will be accurate only if the active groove has 6 ticks per note step. If the groove has some other number of ticks per note step, the BPM value should be adjusted according to the formula  $lsdj\_bpm = (desired\_bpm \times ticks\_per\_step)/6$ .

Example:

**T80** set tempo to 128 (\$80) BPM

## 5.16 V: Vibrato

Vibrate pitch. This command has no effect on noise instruments.

Example:

```
V42 period=4, depth=2
```

## 5.17 W: Wave

The *W* command is used to select one of the four preset pulse waveforms. It can only be used with pulse instruments.

## 5.18 Z: RandomiZe

The *Z* command can be used in the phrase and table screens. It repeats the last non-*Z* command issued in a phrase in the current channel, using the then used command value added with a random number between 0 and the given *Z* command value.

Note: Randomize does not work with Hop, Groove and Delay commands at the moment.



# Chapter 6

## Synchronization

LSDj can be synchronized with other devices, so that it is possible to run both in exactly the same tempo. You can activate synchronization by changing the SYNC mode in the project screen.

**IMPORTANT:** When running synchronized, use a groove based on 6 ticks/step. Otherwise, the resulting speed might be wrong.

### 6.1 Game Boy to Game Boy Sync

LSDj implements Game Boy to Game Boy sync. This requires two Game Boys, two LSDj cartridges and one Nintendo Game Link cable.

#### 6.1.1 Activating Sync

Make sure that both Game Boys are turned off. Connect the Game Boys using the link cable. Now, turn on the Game Boys, and go to the project screens.

In the project screen, you'll find a SYNC parameter, which can be adjusted by pressing A+LEFT/RIGHT. Set the first Game Boy to MASTER and the second Game Boy to SLAVE. Now, the second Game Boy will receive ticks from the first Game Boy through the link cable, ensuring that they will play at the same tempo.

The sync works in two different ways, depending on whether the sequencer is in live mode or not...

### 6.1.2 Using Sync with Both Carts in Song Play Mode

Press START on the slave Game Boy. It will display the text WAIT in the bottom right corner, indicating that it is waiting for tick signals from the master Game Boy. Now, press START on the master Game Boy, and the slave Game Boy will start playing on the same song position as the master Game Boy.

Pressing START again on the master Game Boy will stop both Game Boys, putting the slave Game Boy in WAIT mode.

### 6.1.3 Using Sync with Both Carts in Live Play Mode

Both Game Boys are operated as usual, the difference being that they stay synced.

Sync will be lost on one occasion only: when the master Game Boy is stopped, and the slave Game Boy is still playing. Then, stop the slave Game Boy and start again.

## 6.2 MIDI Sync

MIDI sync requires a special MIDI sync cable for Game Boy. For information on how to build a MIDI to Game Boy adapter, please refer to the website at <http://www.littlesounddj.com>.

Usage: Plug in the sync device before turning on your Game Boy. Then, set LSDj to MIDI slave sync mode. Pressing START will now make LSDj wait for and sync with any incoming MIDI clock signals. LSDj should use grooves based on 6 ticks.



TIP!

- *When LSDj is slave, it is possible to temporarily play slower or faster by pressing A+LEFT/RIGHT on tempo in project screen. This can be very useful when being hooked up to some external hardware that has drifted slightly out of sync.*



## 6.3 Nanoloop Sync


Nanoloop is a Game Boy music program that can be found on <http://www.nanoloop.de>. Nanoloop can sync to LSDj using a normal Nintendo Game Link cable.

Usage: Set LSDj to NANO master sync mode, and set Nanoloop to MIDI slave mode. LSDj should use grooves based on 6 ticks.

## 6.4 Analog In

LSDj can sync to music equipment that sends analog sync signals. This sync mode has been tested with the Korg Volca series, but works with other gear too; you can find a list at [http://littlesounddj.wikia.com/wiki/Analog\\_Sync\\_Compatibility](http://littlesounddj.wikia.com/wiki/Analog_Sync_Compatibility).

A cable should be easy to make, since no particular electronics are needed: all it takes is to splice a Nintendo Game Link Cable and a 3.5mm mini plug cable together. The wires should be connected as shown in the below diagram: GND goes to GND, CLK goes to CLK.




As a clarification, the above diagram is looking at the cable, and the wires are probably not red and blue in reality.

Once the cable is built, connect it to the Game Boy serial port and the SYNC OUT of your synthesizer. In project screen, set LSDj to ANALOG sync mode. The TICKS/STEP setting controls how many LSDj ticks should be generated for each incoming sync signal. Depending on the synthesizer, it may be necessary to change this setting to make LSDj run at the right speed. For Korg Monotribe, it should typically be set to 6, whereas for Korg Volca, it should be C.

## 6.5 Analog Out

Analog Out works similar to Analog In, except that in this mode, LSDj is responsible for sending the sync signal. The cable is different than the one used for Analog In. Build it by connecting the wires as follows:



As a clarification, the above diagram is looking at the cable, and the wires are probably not red and blue in reality. This cable should be connected to SYNC IN of your synthesizer.

## 6.6 Keyboard Control

The KEYBD sync mode is not really about synchronization. Instead, it allows connecting a standard PC keyboard to the Game Boy, so it can be played as a piano. This is useful for live shows and improvisation. For information on how to build a PC keyboard to Game Boy adapter, please refer to the website at <http://www.littlesounddj.com>.

Important: To get a sound when playing on the keyboard, the sequencer must already be running. (Press START first!) The notes you play will be played back on the next step in the phrase sequencer. To get finer timing, use a faster groove for the phrase you are playing.

### 6.6.1 Keyboard Note Layout




Figure 6.1: PC Keyboard Map

SPACE play using custom table

F1/F2 octave down/up

**F3/F4** instrument down/up

**F5/F6** select custom table to assign to SPACE

**F8** change pulse instrument playback channels (PU1, PU2, PU1+2)

**F9-F12** toggle channel mute (switches on key press)

**CTRL+(F9-F12)** tap channel mute (switches on key press and release)

**CURSOR** move around cursor

**ENTER** play chain

**CTRL+ENTER** stop chain

**PAGE UP/DOWN** B+UP/DOWN



# Chapter 7

## Speech Programming

### 7.1 Introduction

Little Sound Dj contains fifty-nine discrete speech sounds (called allophones), stored in the first four kit banks. By combining these sounds, it is possible to create any English word or phrase.

### 7.2 Linguistics

A few basic linguistic concepts will help you create your own library of words. First, there is no one-to-one correspondence between written letters and speech sounds; secondly, speech sounds are acoustically different depending on their position within a word.

The first problem compares to the problem that a child encounters when it learns to read. Each sound in a language may be represented by more than one letter, and conversely, each letter may represent more than one sound. Because of these spelling irregularities, it is necessary to think in terms of sounds, not letters, when using allophones.

The second, and equally important, point to understand is that the acoustic signal of a speech sound may differ depending on its position within a word. For example, the initial K sound in *coop* will be acoustically different from the K's in *keep* and *speak*.

### 7.3 Programming Words

Little Sound Dj has a special speech instrument. It is locked to instrument number \$40 and can be used in the wave channel. It contains a set of 42

words, mapped out from note C-3 to note F-6.

INSTRUMENT 40			PU1
TYPE	SPEECH		
C#3	D 4	E 5	J 128
C#3	D#4	F 5	
D 3	E 4	F#5	1
D#3	F 4	G 5	2
E 3	F#4	G#5	W
F 3	G 4	A 5	H
F#3	G#4	A#5	
G 3	A 4	B 5	
G#3	A#4	C 6	
A 3	B 4	C#6	
A#3	C 5	D 6	
B 3	C#5	D#6	
C 4	D 5	E 6	
C#4	D#5	F 6	

Figure 7.1: Speech Instrument Screen

WORD	C	3	PU1
	PHN	LEN	
0	LL-	02	
1	IH-	06	
2	TT2	03	J 128
3	EL-	08	
4	SS-	04	
5	AW-	08	
6	NN1	05	
7	DD1	03	
8	DD2	03	
9	IY-	08	
A	JH-	05	
B	EY-	08	
C	---	00	
D	---	00	
E	---	00	
F	---	00	

Figure 7.2: Example Word

If you want to edit a word, press SELECT+RIGHT to get to the word screen. It has two columns; the left column contains the allophones to be played, the right column sets duration. The word in figure 7.2 is programmed to say "Little Sound Dj."

In order to make things easy to remember, it is possible to rename the words by tapping A in the speech instrument screen. If you want to, it is also possible to cut and paste words in the speech instrument screen.

## 7.4 Guidelines for Using the Allophones

Allophones marked with \* loop indefinitely.

### 7.4.1 Short vowels

\*IH sitting, stranded

\*EH extent, gentlemen

\*AE extract, acting

\*UH cookie, full

\*AD talking, song

\*AX lapel, instruct

### 7.4.2 Long vowels

IY treat, people, penny

EY great, statement, tray

AY kite, sky, mighty

OI noise, toy, voice

UW1 after clusters with YY: computer

UW2 in monosyllabic words: two, food

OW zone, close, snow

AW sound, mouse, down

EL little, angle, gentlemen

### 7.4.3 R-colored vowels

ER1 letter, furniture, interrupt

ER2 monosyllables: bird, fern, burn

OR fortune, adorn, store

**AR** farm, alarm, garment

**YR** hear, earring, irresponsible

**XR** hair, declare, stare

#### 7.4.4 Resonants

**WW** we, warrant, linguist

**RR1** initial position: read, write, x-ray

**RR2** initial clusters: brown, crane, grease

**LL** like, hello, steel

**YY1** clusters: cute, beauty, computer

**YY2** initial position: yes, yarn, yo-yo

#### 7.4.5 Voiced fricatives

**VV** vest, prove, even

**DH1** word-initial position: this, then, they

**DH2** word-final and between vowels: bathe, bathing

**ZZ** zoo, phase

**ZH** beige, pleasure

#### 7.4.6 Voiceless fricatives

**\*FF** fire, fox

**\*TH** this, they

**\*SS** sit, smile

**SH** shirt, leash, nation

**HH1** before front vowels: YR, IY, IH, EY, EH, XR, AE

**HH2** before back vowels: UW, UH, OW, OY, AO, OR, AR

**WH** white, whim, twenty



### 7.4.7 Voiced stops

**BB1** final position: rib; between vowels: fibber, in clusters: bleed, brown

**BB2** initial position before a vowel: beast

**DD1** final position: played, end

**DD2** initial position: down; clusters: drain

**GG1** before high front vowels: YR, IY, IH, EY, EH, XR

**GG2** before high back vowels: UW, UH, OW, OY, AX; and clusters: green, glue

**GG3** before low vowels: AE, AW, AY, AR, AA, AO, OR, ER; and medial clusters: anger; and final position: peg

### 7.4.8 Voiceless stops

**PP** pleasure, ample, trip

**TT1** final clusters before SS: tests, its

**TT2** all other positions: test, street

**KK1** before front vowels: YR, IY, IH, EY, EH, XR, AY, AE, ER, AX; initial clusters: cute, clown, scream

**KK2** final position: speak; final clusters: task

**KK3** before back vowels: UW, UH, OW, OY, OR, AR, AO; initial clusters: crane, quick, clown, scream

### 7.4.9 Affricates

**CH** church, feature

**JH** judge, injure

**7.4.10 Nasal**



**MM** milk, alarm, example




**NN1** before front and central vowels: YR, IY, IH, EY, EH, XR, AE, ER, AX, AW, AY, UW; final clusters: earn




**NN2** before back vowels: UH, OW, OY, OR, AR, AA




# Chapter 8




## The Sample Kits



Machine	Year	Info
SP0256-AL2 General Instruments	1981	 <p>The SP0256-AL2 Speech Processor IC contains a programmable digital filter that can be made to model a vocal tract. The 16k ROM stores both data and instructions. The pulse width modulated output can produce speech with a frequency range of 5kHz and a dynamic range of 42 dB.</p>
TR-606 Roland	1981	 <p>The Roland TR-606 Drumatix is a programmable analogue drum machine. It was designed to couple with the TB-303 Bassline. The TR-606 has a very original sound and remains popular today.</p>

Machine	Year	Info
TR-707 Roland	1984	 <p data-bbox="655 712 1353 860">The Roland TR-707 has the same functions as the TR-909 with all PCM sounds. Starting with this model, Roland began using an LCD display to show the rhythm matrix and tempo.</p>
TR-727 Roland	1985	 <p data-bbox="655 1205 1353 1352">The Roland TR-727 is identical to the TR-707, with the exception that its sounds are Ethnic/Latin percussion. It is meant to complement a rhythm section, rather than be a main unit.</p>
TR-808 Roland	1980	 <p data-bbox="655 1736 1353 1883">The Roland TR-808 has played a defining role for the 80's Hip Hop and Electro movement. It is still highly popular, thanks to its unmistakably original sounds.</p>

Machine	Year	Info
TR-909 Roland	1983	 <p>The Roland TR-909 is one of the most popular drum machines ever. It has PCM sounds for cymbal and hi-hat, but all other instruments still come from analogue circuitry. The sounds are very useful for House and Techno music.</p>
CR-78 Roland	1978	 <p>The Roland CR-78 is perhaps the most luxurious rhythm machine ever made. The guiro and tambourine are still unique as of today, and bass, snare and bongos sound very soft and rich.</p>
CR-8000 Roland	1981	 <p>The Roland CR-8000 was introduced after the TR-808 – it has the same analog engine. The hi-hat sounds more realistic than older rhythm machines, but the hand clap sounds like an electric snare.</p>

Machine	Year	Info
DR-55 Boss	1979	 <p>The Boss Dr. Rhythm range of drum machines is especially designed for guitar players who need a mobile drummer. The DR-55 is a simple analogue drum machine with a very rough and direct sound.</p>
DR-110 Boss	1983	 <p>The DR-110, the successor of the DR-55, has analogue sound but is programmed digitally using a LCD rhythm matrix. It quite possibly has the best analogue handclap ever.</p>
LinnDrum	1982	 <p>The LinnDrum originally sold for \$3,000 and about 5,000 units were produced. It provided the rhythm tracks of many 1980's hit records.</p>

Machine	Year	Info
Rhythm Ace	1973	 <p data-bbox="568 689 1267 880">Ace Tone was the first company to produce electric rhythm boxes in Japan. In the UK, Bentley Pianos (who put stickers on all their products) distributed Ace Tone, and thus the machine is also known as the Bentley Rhythm Ace.</p>
Tom Sequential Circuits	1984	 <p data-bbox="568 1200 1267 1346">The sounds are a bit dirty and harsh sounding, especially next to its older brother Drumtraks, but that also gives Tom its character. The snare sounds like nothing else on this planet - it's electric!</p>
Acieed House	1990's	 <p data-bbox="568 1637 1267 1742">This set of vocal samples was derived from a bunch of popular Acid House tracks. Can you dig it?</p>

Machine	Year	Info
Ghetto Bass	1990's	 <p data-bbox="679 869 1386 943">A bunch of samples derived from classic Detroit/Chicago ghetto house tracks.</p>
Animals Bud Melvin	2004	 <p data-bbox="679 1413 1386 1527">The winner of the 2004 Animal Sample Compo. A great selection of domestic animals. The Levi's 501 of animal kits!</p>